

机器人中央调度管理系统环境部署

Robot central management system environment setup

Document Version	v2.3	
Applicable System Version	Robot Management v2.3	Central System
Last Updated	July 19, 2026	

Contents

1. Preparation of software installation packages.....	2
2. Set up the Java runtime environment.....	3
3. Install the Mysql database service	5
4. Install the database client.....	7

部署本系统所需要的系统最低配置要求如下所示：

- (1) 操作系统(64 位或 32 位)：Windows 10
- (2) 中央处理器：Intel 酷睿 i5 8 代及以上
- (3) 内存：8GB 及以上
- (4) 硬盘空间：C 盘空间不低于 20GB
- (5) 显示器分辨率：1500*800 及以上
- (6) 网卡：可以正常与机器人无线通讯
- (7) 浏览器：建议安装 Google 或 Microsoft 浏览器

The minimum system configuration requirements for deploying this system are as follows:

- (1) Operating system (64-bit or 32-bit) : Windows 10
- (2) Central Processing Unit: Intel Core i5 8th generation or above
- (3) Memory: 8GB or more
- (4) Hard disk space: The space on the C drive should be no less than 20GB
- (5) Monitor resolution: 1500*800 or above
- (6) Network card: It can communicate wirelessly with the robot normally
- (7) Browser: It is recommended to install Google or Microsoft browsers

1. 软件安装包准备

1. Preparation of software installation packages

(1)解压文件 envware.zip, 得到如下文件夹【进入该文件夹】,主要安装 如下 3 个文件;

(1)Extract the file "envware.zip", and you will get the following folders [enter this folder]. The main installation involves the following 3 files;

 dbeaver-ce-23.1.4-x86_64-setup.exe	2024/3/30 11:17	应用程序	117,037 KB
 jdk-17.0.10_windows-x64_bin.exe	2024/3/30 11:18	应用程序	157,238 KB
 mysql-installer-community-8.0.37.0....	2024/6/1 21:09	Windows Install...	303,240 KB

2. 搭建 Java 运行环境


2. Set up the Java runtime environment

(1) 安装 jdk (java 开发工具包)

(1) Install jdk (java Development Kit)

①双击文件jdk-17.0.10_windows-x64_bin.exe；一直点击下一步即可安装完成；

①Double-click the file "jdk-17.0.10_windows-x64_bin.exe"; just keep clicking "Next" until the installation is completed.




(2) 验证是否安装成功

(2) Verify whether the installation is successful

①Win+r 组合键打开运行窗口，输入 cmd，然后回车

①Press the Win+r key combination to open the Run window, type cmd, and then press Enter



②在命令行输入 java -version; 出现如下图所示内容, 表示 java 环境安装成功。

②Enter "java -version" in the command line; the following content as shown in the figure will appear, indicating that the Java environment has been installed successfully.

```
C:\Windows\system32\cmd.e  x  +  v

Microsoft Windows [版本 10.0.22621.3880]
(c) Microsoft Corporation。保留所有权利。

C:\Users\31633>java -version
java version "17.0.10" 2024-01-16 LTS
Java(TM) SE Runtime Environment (build 17.0.10+11-LTS-240)
Java HotSpot(TM) 64-Bit Server VM (build 17.0.10+11-LTS-240, mixed mode, sharing)

C:\Users\31633>
```

3. 安装 Mysql 数据库服务

3. Install the Mysql database service

①双击文件mysql-installer-community-8.0.37.0.msi,按照这个规则(有 next 点 next, 有 execute 点 execute, 有 finish 点 finish) , 即可完成数据库服务的安装。


①Double-click the file "mysql-installer-community-8.0.37.0.msi", and follow this procedure (click "Next" when there is a "Next" option, click "Execute" when there is an "Execute" option, and click "Finish" when there is a "Finish" option), and the database service installation can be completed.

注意事项

Notes

①如图所示, 该步骤需要设置数据库密码, **一定要**将密码设置为 **123456**, 调度系统通过此密码与数据库建立联系, 否则调度系统运行不起来。

①As shown in the figure, this step requires setting a database password. It is essential to set the password to 123456. The dispatching system will establish contact with the database through this password; otherwise, the dispatching system will not be able to run.




(1)验证是否安装成功

(1)Verify whether the installation was successful

①按下 "win" 键，输入 "MySQL 8.0 Command Line Client" ， 点击打开

①Press the "win" key, enter "MySQL 8.0 Command Line Client", and click to open




②输入刚刚设置的密码 123456，回车

②Enter the password you just set, 123456, and press Enter

③出现如下图所示内容，即数据库服务安装成功

③If the content as shown in the following figure appears, it indicates that the database service has been successfully installed



```
MySQL 8.0 Command Line CLI
Enter password: *****
Welcome to the MySQL monitor.  Commands end with ; or \g.
Your MySQL connection id is 221
Server version: 8.0.37 MySQL Community Server - GPL

Copyright (c) 2000, 2024, Oracle and/or its affiliates.

Oracle is a registered trademark of Oracle Corporation and/or its
affiliates. Other names may be trademarks of their respective
owners.

Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.

mysql> |
```

4. 安装数据库客户端

(1) 保证现场网络良好，使用 DBeave 操作数据库。以管理员身份运行 dbeaver-ce-23.1.4-x86_64-setup.exe 按照这个规则：【有 下一步 点 下一步；有 我接受 点 我接受；有 安装 点 安装；有 完成 点 完成；】详细步骤如下图：

4. Install the database client

(1) Ensure that the on-site network is in good condition and use DBeave to operate the database. Run dbeaver-ce-23.1.4-x86_64-setup.exe as an administrator. Follow this rule: [Next Click Next; I accept Click I accept; Install

Click Install; Complete Click Complete;]. The detailed steps are as shown in the following figure:

(1) 连接数据库服务到客户端


A、连接数据库服务

找到刚刚安装的 DBeaver 软件，双击运行，按下图内容进行设置：选择数据库类型：mysql，密码：123456。

(1) Connect the database service to the client

A、Connect to the database service

Locate the newly installed DBeaver software, double-click to run it, and follow the steps as shown in the picture to set up: Select the database type as "mysql", and the password as "123456".



B、测试数据库连接

输入完成后，点击测试连接，中间出现需要下载的提示，直接单击进行下载即可；出现“已连接”，表示配置正确，已经连接到数据库；然后点击完成。

B、 Testing database connection

After inputting the information, click on "Test Connection". A prompt will appear asking you to download. Just click to download it directly. When you see "Connected", it indicates that the configuration is correct and you have successfully connected to the database. Then click "Finish".




C、配置调度的数据库文件

1、点击“新建数据库”，输入数据库名称“Ezhan”，数据库名称一定要是这个，否则会报错

C、Configure the database file for scheduling

1、Click "New Database", enter the database name "Ezhan", and the database name must be this; otherwise, an error will be reported




(2) 导入数据

(2) Import data

①新建 SQL 编辑器，如下图所示


①new SQL editor has been created, as shown in the following picture.



②打开 Robot central control system 文件夹下的.sql 后缀的文件，按快捷键 ctrl+A

全选，ctrl+C 复制


②Open the files with the ".sql" extension in the "Robot central control system" folder, select all using the shortcut key "ctrl+A", and then copy them with "ctrl+C".



③回到软件 DBeaver 的 SQL 编辑器，按快捷键 `ctrl+v` 粘贴；然后点击执行，如图所示

③Return to the SQL editor of the software DBeaver, and press the shortcut key

"`ctrl+v`" to paste. Then click "Execute", as shown in the figure.



至此，数据库配置完成。

At this point, the database configuration is completed.